

## 2. the installation CanMV IDE development software

### 2. the installation CanMV IDE development software


- 2.1 download CanMV IDE
- 2.2 interface functional description
- 2.3 connected devices
- 2.4 temporary run the program
- 2.5 boot to run the program


### 2.1 download CanMV IDE

1. CanMV IDE GitHub address, according to their own system to download the corresponding software package is installed, here to win10 as an example:

[https://github.com/kendryte/canmv\\_ide/releases](https://github.com/kendryte/canmv_ide/releases)

Nov 21, 2022

 kendryte747

 v2.9.2-1

 626670d

Compare

## v2.9.2-1

Latest

Add update examples from github/gitee, user should install git to system PATH.

sha2

737ef5835faeed9be89db1a2e6d9557640717f6563931a21f0d4962292e7d97d canmv-ide-linux-x86\_64-v2.9.2-1-g626670d.run

2d668984080c7a03fd3793cabdf3d96c8745ee539cbf9021e9e43a219c51f2b2 canmv-ide-mac-2.9.2-1-g626670d.dmg

5a111b83f2fc3802b29e2bdc802cc0809a70e5d7e79ee65362c3a641916e36cc canmv-ide-windows-v2.9.2-1-g626670d.exe

#### Assets 5

 canmv-ide-linux-x86_64-v2.9.2-1-g626670d.run	136 MB	Nov 21, 2022
 canmv-ide-mac-2.9.2-1-g626670d.dmg	137 MB	Nov 21, 2022
 canmv-ide-windows-v2.9.2-1-g626670d.exe	104 MB	Nov 21, 2022
 Source code (zip)		Nov 21, 2022
 Source code (tar.gz)		Nov 21, 2022



3. After the download gets canmv-ide-a windows-vx. x. x-gxxxxxx. exe file, double-click to open the installation package.

**Setup - CanMV IDE**

Installation Folder

Select Components

License Agreement

Start Menu shortcuts

Ready to Install

**Setup - CanMV IDE**

Welcome to the CanMV IDE Setup Wizard.

Next

Quit

Modify the installation path

← CanMV IDE 2.9.2 Setup

Setup - CanMV IDE

**Installation Folder**

License Agreement

Start Menu shortcuts

Ready to Install

Installing

**Installation Folder**

Please specify the directory where CanMV IDE will be installed.

C:/Program Files/CanMV IDE

Browse...

Next

Cancel

← CanMV IDE 2.9.2 Setup

Setup - CanMV IDE

Installation Folder

**License Agreement**

Start Menu shortcuts

Ready to Install

Installing

**License Agreement**

Please read the following license agreement. You must accept the terms contained in this agreement before continuing with the installation.

This is the GNU General Public License version 3, annotated with The Qt Company GPL Exception 1.0:



-----

The Qt Company GPL Exception 1.0


☒ I accept the license.

Next


Cancel



Wait for the installation Assembly can be completed.



## 2.2 interface functional description



Area ① menu bar: the operation file, use tools, etc.

Area ② shortcut buttons: regional ① file And edit Some of the features of the shortcut.

Area ③ connect the device: connect the device and program the control button.

Region ④ code editing area: edit to run the code.

Region ⑤ serial terminal: display the serial port to print debugging information.


Region ⑥ image preview: display the camera image preview.

Region ⑦ firmware information: shows the connection of the serial number and the firmware information.


## 2.3 connected devices

The K210 module via the microUSB cable is connected to the computer USB port.

Then click on the CanMV IDE in the lower left corner of the Connect button




The pop-up select the serial port, select the K210 module corresponding to the serial number. If there are multiple serial ports, first determine the corresponding serial port number and then click OK to open.



If the connection is not on, you can click Advanced settings, Select the Mode to 2.

A successful connection will be the icon changes to a connected state, while the gray play button becomes green.




## 2.4 temporary run the program


Note: This step is to run the program, disconnect, press the reset button or shut down, the program lost not saved.

After the connection is complete, you can see in the lower left corner of the connection icon turns into a connected symbol.

If there is no open routine, you can open the file->examples->Basics->helloworld.py




Click on the green play button to run the program.



At this point you can see the LCD display the camera screen, while the IDE the upper right corner also display the camera screen.

The green play button icon turns into the red stop button, one click can stop the running program.




## 2.5 boot to run the program

Note: This step of the procedure to re-power automatically after running.

In keeping connected to the case, click on Tools->Save the currently open script of main.py to CanMV Cam





Click Yes to save the program, after completion, disconnect, or press the reset button, the program will run automatically.

If insert the TF card, the program priority saved to the TF card, and the priority to run the TF card in the main. py file.

